

# CLM LICENSE ACTIVATION MIGRATE USB DONGLE TO EID MAP360 2021

# 1. Locate your Entitlement ID (EID)

- when it has to be right 

Leica Geosystems  
**Entitlement Certificate**

Product: MAP360 Base  
Entitlement ID: 00107-79315-00032-11191-15852

Certificate  
Leica Geosystems grants you the right to activate the following product(s):

Article No.	Description	Quantity
5308173	MAP 360 Sketch (1yr)	1
5310039	MAP360 Base	1

Maintenance End:

Activation  
The Entitlement ID will be required to activate the licenses during the installation process.  
If you have any questions, please contact your local Leica Geosystems Sales & Support.

Software License Agreement  
Rights and restrictions on the use of this product are set forth in the Leica Geosystems Software License Agreement available at:  
<http://www.leica-geosystems.com/swlicense>

Registration  
By registering your products in the online customer internet platform myWorld @ Leica Geosystems, full details about your purchased products are available at your convenience 24/7.  
Register today at <https://myworld.leica-geosystems.com>

Leica Geosystems AG  
Max-Schmidstr. 204  
8430 Leoben  
+43 71 727 3131  
Österreich  
[www.leica-geosystems.com](http://www.leica-geosystems.com)

Customers entitled to a free migration to CLM will receive an Entitlement Certificate.

The certificate will be mailed or emailed to you.

The EID is listed at the top of the document with the specific products that it entitles the user to listed below.

Customers who have been granted an EID to replace their Map360 Dongle will receive their EID via email and mailed letter.

- when it has to be right




# Remove your USB Dongle

Since you will be migrating to an electronic license, you do not need your USB Dongle anymore.

Please remove it from your computer before continuing.

## 2. Download and Install Map360




The Leica Client License Manager (CLM) is installed with Map360.

If you have not already done so, you will need to download Map360 and install it. Once installed run the program.

On the start-up screen, select Leica CLM and select the CLM Manager button.


This will start the CLM program. Leave Map360 running in the background.

# 3. Add your License (1 of 2)




1. Select **Add** from the top of the CLM interface.
2. Add your EID including all dashes.
  1. To enter multiple EIDs, separate them with a semicolon “;”.
  2. Note: do not add any spaces between EIDs.
3. Select **Add** at the bottom of the window.

### 3. Add your License (2 of 2)



Note: You must have an internet connection to enable your license. If you do not, or your IT security prevents you from connecting to the internet, Please select **Do you want to activate a license offline?** at the bottom of the window for support.

# 4. Activate your license




The license will go through an activate stage.

Once complete, your license will be listed in your Licenses section. Expand the license to see its contents and its expiration or maintenance date.

You can now close the CLM program and return to Map360.

## 5. Reload EID




Close the CLM program.

Switch to Map360 and select Reload Entitlements.

Your license details will be displayed. Select the license option you want to use.


Press Run to start the program with your chosen license.

## 6. Check that the EID is in Use (1 of 2)



Click on the Help Ribbon and select About Map360.

## 6. Check that the EID is in Use (2 of 2)



In the About Map360 screen, confirm that the correct EID serial number is displayed, along with the correct maintenance expiry date.

Press OK to continue.